Canon	EOS Utility Instruc	tion	Manual Windows	Osum/Table of
Canon Utilities		Table	of Contents Introduction	Cover/Table of Contents
• EOS Utility 1.0 Compatible Mo		1	Downloading Images from the Camera	Downloading Images from the Camera
• EOS-1D Mark II N • EOS-1Ds Mark II	• EOS 5D • EOS 30D	2	Setting the Cameras other than the EOS-1D Series Cameras	Setting the Cameras other than the EOS-1D Series Cameras
 EOS-1D Mark II EOS-1Ds EOS-1D 	 EOS 20D EOS 10D EOS DIGITAL REBEL XT/350D DIGITAL 	3	Setting the EOS-1D Series Cameras	Setting the EOS-1D Series Cameras
	 EOS DIGITAL REBEL/300D DIGITAL EOS D60 	4	Remote Shooting	Remote Shooting
	• EOS D30		Troubleshooting	Troubleshooting
			Index	Index



READ CAREFULLY BEFORE USING!

CANON SOFTWARE LICENSE AGREEMENT

IMPORTANT - READ THIS AGREEMENT BEFORE USING THE SOFTWARE ON THE CD-ROM IN THIS BOX. BY USING THE SOFTWARE, YOU AGREE TO BE BOUND BY THE TERMS OF THIS AGREEMENT.

This is a license agreement (the [Agreement]) between you and Canon Inc. ([Canon]).

IF YOU DO NOT AGREE TO THE TERMS AND CONDITIONS OF THIS AGREEMENT, DO NOT USE THE SOFTWARE PROGRAM ON THE CD-ROM AND THE USER MANUAL IN THIS BOX (COLLECTIVELY, THE [SOFTWARE]) AND RETURN THE SOFTWARE WITHIN 30 DAYS FROM THE DATE OF PURCHASE TO YOUR POINT OF PURCHASE FOR A REFUND.

In consideration of the right to use the SOFTWARE, you agree to abide by the terms and conditions of this Agreement.

1. LICENSE: Canon grants you the non-exclusive right to use the SOFTWARE only on a single computer. You may physically transfer the SOFTWARE from one computer to another provided that the SOFTWARE is used on only one computer at a time. You shall not install or use the SOFTWARE on a network, multiple CPU, multiple site arrangement, or any other hardware configuration where the SOFTWARE is accessible to more than one CPU or to more than one user.

YOU SHALL NOT ASSIGN, SUBLICENSE, RENT, LEASE, LOAN, CONVEY OR OTHERWISE USE, TRANSFER, COPY, TRANSLATE, CONVERT TO ANOTHER PROGRAMMING LANGUAGE, ALTER, MODIFY, DECOMPILE OR DISASSEMBLE THE SOFTWARE, IN WHOLE OR IN PART, EXCEPT AS EXPRESSLY PROVIDED IN THIS AGREEMENT.

- 2. BACK-UP COPY: You may make one copy of the SOFTWARE solely for back-up purposes, or copy the SOFTWARE onto the permanent storage device (e.g. a hard disk) of your computer and retain the original for back-up purposes. Any other copying of the SOFTWARE is a violation of this Agreement. You must reproduce and include the copyright notice on the back-up copy.
- SUPPORT AND UPDATES: Canon is not responsible for providing maintenance or support for use of the SOFTWARE. No updates, fixes or support will be made available for the SOFTWARE.
- 4. LIMITED WARRANTY AND LIMITATION OF LIABILITY: It is your responsibility to choose, maintain and match the hardware and software components of your computer system. Thus Canon does not guarantee uninterrupted service or correction of errors or that the functions or performance of the SOFTWARE will meet your requirements. THE SOFTWARE IS LICENSED ON AN [AS IS] BASIS AND WITHOUT WARRANTY OF ANY KIND. The CD-ROM storing the SOFTWARE is warranted only against defective material under normal use for a period of ninety (90) days after purchase from an authorized Canon dealer as evidenced by your sales receipt. Your sole remedy for a defective CD-ROM shall be replacement of the same without charge when returned by you at your expense to your point of purchase and proven to be defective upon inspection. The replacement CD-ROM will be warranted for the remainder of the original ninety (90) day warranty period of the defective CD-ROM. The limited warranty does not apply if the failure of the CD-ROM resulted from accident, abuse or misapplication of the SOFTWARE and shall not extend to anyone other than the original user of the SOFTWARE.

EXCEPT AS SPECIFICALLY SET FORTH IN THIS PARAGRAPH 4, CANON, CANON'S SUBSIDIARIES, DISTRIBUTORS AND DEALERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, WITH RESPECT TO THE SOFTWARE. NEITHER CANON NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS IS LIABLE FOR ANY DAMAGES HOWSOEVER CAUSED, INCLUDING WITHOUT LIMITATION, DIRECT, CONSEQUENTIAL OR INCIDENTAL LOSS OR DAMAGE INCLUDING LOSS OF PROFITS, EXPENSE OR INCONVENIENCE HOWSOEVER CAUSED OR ARISING OUT OF THE SOFTWARE OR THE USE THEREOF.

NEITHER CANON, NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS SHALL HAVE ANY OBLIGATION TO INDEMNIFY YOU AGAINST ANY CLAIM OR SUIT BROUGHT BY A THIRD PARTY ALLEGING THAT THE SOFTWARE OR THE USE THEREOF INFRINGES ANY INTELLECTUAL PROPERTY OF SUCH THIRD PARTY.

- 5. TERM: This Agreement is effective upon your using the SOFTWARE and remains in effect until expiration of all copyright interests in the SOFTWARE unless earlier terminated. You may terminate this Agreement by destroying the SOFTWARE. This Agreement will also terminate without notice to you if you fail to comply with any of the terms of this Agreement and you must then promptly return the SOFTWARE. In addition, Canon may enforce its other legal rights.
- 6. U.S. GOVERNMENT RESTRICTED RIGHTS NOTICE: The SOFTWARE is provided with restricted rights. Use, duplication or disclosure is subject to restrictions as set forth in either subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer software clause at DFARs 252.227-7013 or subparagraph (c) (1) and (2) of the Commercial Computer Software Restricted Rights Clause at FAR 52.227-19, as applicable.
- 7. SEVERABILITY: In the event that any provision of this Agreement is declared or found to be illegal by any court or tribunal of competent jurisdiction, such provision shall be null and void with respect to the jurisdiction of that court or tribunal and all the remaining provisions of this Agreement shall remain in full force and effect.
- 8. CONTROLLING LAW: The terms of this Agreement as it relates to purchases of the Software in the United States of America shall be governed and construed in all respects in accordance with the laws and regulations of the State of New York, without reference to choice of law principles. The terms of this Agreement as it relates to purchases of the Software in Canada shall be governed by the laws of the province of Ontario.
- 9. OWNERSHIP: All rights, including but not limited to copyrights and trade secret rights, to the SOFTWARE belong to Canon, its affiliated corporations and third party licensors. Your use of the SOFTWARE is subject to the United States, Canada and other applicable copyright and trademark laws and nothing in this Agreement constitutes a waiver of the rights of Canon, its affiliated corporations and third party licensors under such laws. Nothing contained in Paragraph 1 shall be construed to give Canon any ownership rights in any images, graphics or textual material that you save in connection with the Software.
- 10.ACKNOWLEDGEMENT: BY USING THE SOFTWARE, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, UNDERSTOOD IT, AND AGREE TO BE BOUND BY ITS TERMS AND CONDITIONS. YOU ALSO AGREE THAT THIS AGREEMENT IS THE COMPLETE AND EXCLUSIVE STATEMENT OF AGREEMENT BETWEEN YOU AND CANON CONCERNING THE SUBJECT MATTER HEREOF AND SUPERSEDES ALL PROPOSALS OR PRIOR AGREEMENTS, VERBAL OR WRITTEN, AND ANY OTHER COMMUNICATIONS BETWEEN THE PARTIES RELATING TO THE SUBJECT MATTER HEREOF. NO AMENDMENT TO THIS AGREEMENT SHALL BE EFFECTIVE UNLESS SIGNED BY A DULY AUTHORIZED OFFICER OF CANON.

ERS	Cover/Table of Contents	
ERS EOF	Introduction	
ffect ′ou o nent s	Downloading Images from the Camera	
vith either at	Setting the Cameras other than the EOS-1D Series Cameras	
to be void f this	Setting the EOS-1D Series Cameras	
cts in o		
o the use ght	Remote Shooting	
nts in	Troubleshooting	

Introduction

This chapter includes information on the precautions to be read before using EOS Utility, how to use this Instruction Manual, the system requirements and the supported image types. It also explains the software features and configuration.

 Click on the item to display its page. 	
About This Manual)-1
System Requirements)-1
Compatible Models and Supported Images)-1
How to Use This Instruction Manual)-2
Software Main Features and Configuration)-3

About This Manual

Thank you for purchasing this Canon product.

Precautions for using this product safely and icons to help you with procedures, etc. are described at the beginning of this Instruction Manual. Please be sure to read these first before proceeding to the information in the other chapters.

- It is prohibited to reproduce, in whole or part, the contents of this Instruction Manual without permission.
- Canon may change without notice the software specifications and contents of this Instruction Manual.
- The software screens and displays printed in this Instruction Manual may differ slightly from the actual software.
- The content of this Instruction Manual has been reviewed thoroughly. However, if you should notice any errors or omissions, please contact a Canon Service Center.
- Please note that irrespective of the above-mentioned, Canon does not take responsibility for the outcome of the operation of the software.

Trademark Acknowledgments

- Canon and EOS are trademarks of Canon Inc.
- IBM is a registered trademark of International Business Machines Corporation.
- Microsoft and Windows are registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- Other names and products not mentioned above may be registered trademarks or trademarks of their respective companies.

System Requirements

OS	Windows XP (Professional/Home Edition), Windows 2000	
Computer	Computer with one of the above OS preinstalled and a USB port as a standard feature or an OHCI-compliant IEEE1394 port * Upgraded machines not supported.	Sett othe Seri
CPU	750MHz Pentium III or higher	Sen
RAM	Minimum 256MB	_
Interface	USB 1.1 to 2.0 Hi-Speed or IEEE1394	
Display	Screen resolution: 1024 x 768 pixels or more Color quality: Medium (16 bit) or more	Sett Seri

Compatible Models and Supported Images

This software supports the following cameras and images.


	Supported Cameras	Supported Images	
EOS-1D Mark II N	EOS 30D		
EOS-1Ds Mark II	EOS 20D		
EOS-1D Mark II	EOS 10D	RAW and JPEG images	
EOS-1Ds	EOS DIGITAL REBEL XT/350D DIGITAL	shot with the camera on	_
EOS-1D	EOS DIGITAL REBEL/300D DIGITAL	the left	
EOS 5D	EOS D60		
-	EOS D30		

Introduction
Downloading Images from the Camera
Setting the Cameras other than the EOS-1D Series Cameras
Setting the EOS-1D Series Cameras
Remote Shooting
Troubleshooting

Cover/Table of Contents



How to Use This Instruction Manual



- For more information on the restrictions of EOS Utility, refer also to the source listed below.
- Readme: Click the [Start] button ► select [All Programs] ([Programs] in Windows 2000) ► [Canon Utilities] ► [EOS Utility] ► [EOS Utility Readme].
- In this manual, the screens used in the examples are from Windows XP.
 Text inside < > in this document indicates the keys on the keyboard and camera button names.
- ▶ in this document indicates the sequence of operation as shown on the right.
 Example: [View] menu ▶ [Display Size] ▶ [Large]





Software Main Features and Configuration


Canon Digital Camera software having the following features and functions is stored on the EOS DIGITAL Solution Disk. Operation is done as shown on this page together with

each software application, centered around EOS Utility.

- : Shows the shot image flow.
- Shows the camera control information from the software.

: Shows software windows and descriptions of operation explained in this manual.

: Shows the Digital Photo Professional and ZoomBrowser EX windows and description of each operation.



0-3

Cover/Table of

Contents

Introduction

Downloading Images from the Camera

This chapter explains preparations necessary to download images from your camera to your computer, and downloading methods. It also explains how to download images using a third-party card reader.

• Click on the item to display its page.

Prepare to Download Images 1-2
Setting a Camera with [Communication] Settings 1-2
Connect the Camera and the Computer and then Start EOS Utility 1-3
Connecting a Camera other than an EOS-1D Series Camera to Your Computer 1-3
Connecting an EOS-1D Series Camera to Your Computer 1-4
Precautions When Connecting the Camera and Computer 1-5
Downloading Images from Your Camera 1-6
Downloading All the Images in a Single Operation 1-6
Downloading Images to Your Computer by Operating the Camera 1-6
Downloading Selected Images 1-7
Downloading JPEG Images Using the PTP Function 1-8
Downloading for Cameras other than the EOS-1D Series Cameras 1-8
Downloading with EOS-1D Series Cameras 1-8
Precautions for the PTP Function 1-9
Downloading Images Using Your Card Reader 1-9
Transferring the Images in a Specified Folder 1-10
Specifying Preferences 1-10

Cover/Table of Contents
Introduction
Downloading Images from the Camera
Setting the Cameras other than the EOS-1D Series Cameras
Setting the EOS-1D Series Cameras
Remote Shooting
Troubleshooting

Cover/Table of



Prepare to Download Images

Setting a Camera with [Communication] Settings

For a camera with [Communication] included as a menu function, you can communicate with EOS Utility to download images to your computer by selecting a [Communication] setting.

- The setting on this page is necessary for the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL and EOS DIGITAL REBEL/300D DIGITAL.
- For cameras other than the above, it is not necessary to perform settings for the camera. Continue with the procedure in "Connect the Camera and the Computer and then Start EOS Utility" (p.1-3).

Check that the camera is not connected to the computer and then set the camera's power switch to <ON>.

Set the camera's [Communication].

• With the EOS 30D, set [**f1** Communication] in menu to [Print/PC].

cameras in the same procedure as the

EOS 30D, using the following for a

Set the [Communication] for other

reference.

 Image

 Date/Time
 '(

 File numbering

 Language

 Video system

 Communication

 Print/PC

 Format
 LAN(WFT-E1)

 Custom Function

Operation window in the EOS 30D

[Communication] settings for different cameras


Camera model	Menu	Setting
• EOS 5D	[ft Communication]	[PC connect.]
• EOS 30D	[ft Communication]	[Print/PC]
• EOS 20D	[ft Communication]	[Normal]
• EOS 10D	[Communication]	[Normal]
• EOS DIGITAL REBEL XT/350D DIGITAL	[ft2 Communication]	[PC connection]
EOS DIGITAL REBEL/300D DIGITAL	[ft2 Communication]	[Normal]

Press the <MENU> button to switch the LCD monitor display off and then set the camera's power switch to <OFF>.

- When setting the [Communication], always ensure that the camera is not connected to the computer beforehand. Setting the [Communication] while the camera is connected to the computer will cause camera and software malfunctions.
- When using the EOS 5D or EOS DIGITAL REBEL XT/350D DIGITAL, the remote shooting function and camera setting function in EOS Utility cannot be used if the camera's [Communication] is set to [Print/PTP].
- When using the EOS 30D, the camera and EOS Utility cannot communicate if the camera's [Communication] is set to [LAN (WFT-E1)].
- When using the EOS 20D, EOS 10D or EOS DIGITAL REBEL/300D DIGITAL, the camera and EOS Utility cannot communicate if the camera's [Communication] is set to [PTP].
- With the EOS 10D, you must change the firmware to version 2.0.0 or later. For details on changing, refer to the Canon's web site.

About the PTP Setting

When using Windows XP, you can also download JPEG images that use the PTP (Picture Transfer Protocol) function (p.1-8).





Connect the Camera and the Computer and then Start EOS Utility


Connecting a Camera other than an EOS-1D Series Camera to Your Computer

Connection procedure for the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL, EOS DIGITAL REBEL/300D DIGITAL, EOS D60 and EOS D30 Before downloading images to your computer or specifying the camera settings, you must connect the camera to your computer with the interface cable supplied with the camera. You can connect the camera while your computer is running.

 For instructions on connecting EOS-1D series cameras and your computer, refer to the next page.


Plug the dedicated cable into the computer.

- Plug the cable into the USB port.
- Refer to the computer User's Manual for information on the terminal areas.



Plug the dedicated cable into your camera.

 Face the < + > mark on the plug to the front of the camera and connect the plug to the camera's < DIGITAL > terminal.



	Set the camera's power switch to <on>.</on>	Cover/Table or Contents
	Dimensional Control Co	Introduction
×t	Stats to download images Image: Stats to download images Image: Stats you select and download images Set up camera/Shoot remotely Image: Stats you camera settings/Remote shooting	Downloading Image from the Camera
	Monitor folder Monitor Folder Preferences Quit	Setting the Cameras other than the EOS-11 Series Cameras
	 → [EOS Utility] starts up and main window is displayed, the camera is ready to communicate with your computer. Proceed to "Downloading Images from Your Camera" (p.1-6) continuously. When the camera selection window appears, select the connected camera and then 	Setting the EOS-1D
	 [EOS Utility] will start up. The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected. 	Series Cameras
	 If the dialog box on the right appears, select [Canon EOS Utility Downloads images from EOS camera] and then click the [OK] button to start [EOS Utility]. If [EOS Utility] does not start, double-click the [EOS Utility]. 	Remote Shooting
	Utility] icon on the desktop or click the [Start] button ► select [All Programs] ([Programs] in Windows 2000) ► [Canon Utilities] ► [EOS Utility] ► [EOS Utility].	Troubleshooting

Index


1-3

Connecting an EOS-1D Series Camera to Your Computer

Connection procedure for the EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II, EOS-1Ds and EOS-1D


Before downloading images to your computer or specifying the camera settings, you must connect the camera to your computer with the dedicated IEEE1394 interface cable supplied with the camera. You can connect the camera while your computer is running.

- For instructions on connecting cameras other than the EOS-1D series cameras and your computer, refer to the previous page.
 - Plug the dedicated cable into the computer.
 - Plug the cable into the IEEE1394 port.
 - Refer to the computer User's Manual for information on the terminal areas.




Plug the dedicated cable into your camera.

- For cameras supplied with the cable protector, attach the cable protector to the camera, and then follow the procedure below to connect the dedicated cable.
- Make sure the $\langle \Box \rangle$ mark on the plug is facing the top of the camera and then connect the plug to the camera's < DIGITAL > terminal.




2	Set the camera's power switch to <on></on>



Camera" (p.1-6) continuously.

[EOS Utility] will start up.

connected.





If the dialog box on the right appears, select [Canon EOS Utility Downloads images from EOS camera] and then click the [OK] button to start [EOS Utility].

communicate with your computer. Proceed to "Downloading Images from Your

• The above window shows information displayable when EOS-1D Mark II N is

connected. The displayed information varies depending on the camera model

When the camera selection window appears, select the connected camera and then


If IEOS Utility does not start, double-click the IEOS Utility] icon on the desktop or click the [Start] button select [All Programs] ([Programs] in Windows 2000) ▶ [Canon Utilities] ► [EOS Utility] ► [EOS Utility].

Device Connected
Select the program to launch for this action:
Canon Camera Window
Canon EOS Utility Downloads images from EOS camera
Microsoft Scanner and Camera Wizard Download pictures from a camera or scanner

OK

Cancel

Always use this program for this acti




Remote Shooting

Precautions When Connecting the Camera and Computer

- You cannot communicate with the camera when you are displaying images through the camera's LCD monitor. Always connect the camera and your computer after turning off the display in the LCD monitor.
 - While the camera and your computer are communicating, the camera's LCD panel may blink.
 - Use only the dedicated cable.
 - With EOS-1D series cameras, if you connect the plug of the dedicated cable into the computer's IEEE1394 port in the reverse direction, the camera or the computer may break down. Confirm that the shape of the plug and the shape of the IEEE1394 port match before connecting.
 - With EOS-1D series cameras, you cannot communicate with EOS Utility even if you connect the USB interface cable supplied with the camera.
 - Push the plug firmly all the way into the socket. Loose connections can cause faults or malfunctions.
 - Do not connect the camera to your computer via a hub. If you do so, the camera may not operate correctly.
 - If you connect multiple USB or IEEE1394 devices (excluding mouse and keyboard) to your computer, the camera may not operate correctly. Disconnect from your computer any USB devices and IEEE1394 connection devices other than the camera.
 - Operation of the Auto power off function will automatically switch the camera off, disabling to communicate with your computer. Set the Auto power off function to [OFF] in advance. For more details, refer to the camera's Instruction Manual supplied with the camera.
 - Do not connect more than one camera to the same computer. The connections may not operate correctly.
 - The camera cannot communicate correctly with multiple softwares. Use one software to communicate with the camera.
 - When unplugging the dedicated cable, be sure to grip the sides of the plug as you pull it out.
 - * If you are using the EOS D60 or EOS D30, pull the plug while pressing the <PUSH> button on it.
 - If you do not perform any operation while the camera and computer are connected, a confirmation message may appear on the computer screen asking whether you wish to continue communicating with the camera for some computer systems. If you do not perform any operation even after this message appears, the communication with the camera is terminated. To re-establish the communication, press the shutter button down halfway or set the camera's power switch to <OFF> and then back to <ON>.
 - Do not put your computer to sleep while it is connected to the camera. If your computer goes into the sleep mode, never disconnect the dedicated cable while your computer is still in the sleep mode. Always wake your computer up while it is connected to the camera. On some types of computer, disconnecting the dedicated cable while your computer is in sleep mode could prevent the computer from waking up correctly. Refer to the computer User's Manual for more information on sleep mode.

- When you connect the camera and your computer, it is recommended that you use the AC Adapter Kit (optional) for the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL, EOS DIGITAL REBEL/300D DIGITAL, the DC Coupler supplied with the camera for the EOS D60 and EOS D30, and the DC Coupler Kit supplied with the camera for EOS-1D series cameras.
 - When connecting the EOS-1D series camera and a computer with a 4-pin type IEEE1394 port, use the EOS-1D series dedicated Canon interface cable (optional) 4pin/4-pin type for the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II, and a 4-pin/6-pin type for the EOS-1Ds and EOS-1D.
 - When using the dedicated cable supplied with the EOS-1Ds or EOS-1D, either plug (6-pin type) can be connected to the computer or your camera.
 - When connecting the dedicated cable to the EOS D60 or EOS D30, insert it with the <▶> mark on the plug matched with the <▶> mark on the < DIGITAL > terminal.





Downloading Images from Your Camera

6

Preferences...

Downloading All the Images in a Single Operation

You can download to your computer all the images saved on a memory card in the camera, in a single operation. You can follow this same procedure when downloading images using a third-party card reader (p.1-9).

Click the [Starts to download images] button.

- The [Save File] dialog box appears and the images are downloaded to the computer.
- The downloaded images are sorted in folders by shot date, and are saved in the [My Pictures] folder on the computer.
- When all the images have been downloaded, the ZoomBrowser EX starts up and the downloaded images are displayed. For further instructions, refer to the ZoomBrowser EX Instruction Manual.
- To exit EOS Utility, click the [Quit] button.
- When disconnecting the interface cable from the camera and computer, be sure to exit EOS Utility and then set the camera's power switch to <OFF> before disconnecting the cable.

🖀 EOS Utility - Canon EOS XXX	>
Downloads using camera	
Press the camera's butte	on
Downloade using comestar	
Starts to download images	
Lets you select and download images	
Set up camera/Shoot remotely	
Camera settings/Remote shooting	
Monitor folder and import images	
Monitor Folder	

The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected.


Quit

In the preferences, only images downloaded for the first time are downloaded and saved in the [My Pictures] folder (you cannot download images previously downloaded). You can change the image download type or the save destination in the dialog box (p.1-10) that appears when you click the [Preferences] button.

You can change the software that starts up when you download images, from ZoomBrowser EX to Digital Photo Professional (p.1-10). However, if you have downloaded images following "Downloading Images Using Your Card Reader" (p.1-9), the software that can start up is limited to ZoomBrowser EX.

Cover/Table of Downloading Images to Your Computer by Operating the Camera Contents With cameras that have the direct image transfer function, you can download to your computer images saved in your camera's memory card by operating the camera. For detailed instructions on the direct image transfer function, refer to the camera's Instruction Manual supplied with Introduction vour camera. This function is compatible with the EOS 30D. Connect the camera and the computer and then start EOS Utility (p.1-3). from the Camera Perform direct image transfer on the camera. → The images from the camera are saved to the computer. • When all the images have been downloaded, ZoomBrowser EX starts up and the downloaded images are displayed. For further instructions, refer to the ZoomBrowser EX Instruction Manual

You can change the software that starts up when you download images, from ZoomBrowser EX to Digital Photo Professional (p.1-10).





Downloading Selected Images

You can display the images saved on a memory card in the camera, select the images you want and download them to your computer. You can follow this same procedure when downloading images using a third-party card reader (p.1-9).

Click the [Lets you select and download images] button.


→ The image download window appears and the images on the memory card are displayed.



The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected.

Select the images to download.

- Click the target image.
- To select multiple images, hold down the <Ctrl> key and click the images.
- To select sequential images, click the first image and then hold down the <Shift> key and click the last image.



Click the [Download Images] button.

→ The [Download image] dialog box appears.

Specify the save destination and then click the [OK] button.

- → The [Save File] dialog box appears and the images are saved in the specified folder.
- When all the images have been downloaded, the ZoomBrowser EX starts up and the downloaded images are displayed. For further instructions, refer to the ZoomBrowser EX Instruction Manual.
- When switching to the main window, select the [Window] menu ▶ [Main Window].
- To exit EOS Utility, click the [File] menu [Exit].
- When disconnecting the interface cable from the camera and computer, be sure to exit EOS Utility and then set the camera's power switch to <OFF> before disconnecting the cable.
- 📱 🗕 [長] is displayed on images previously downloaded to your computer.
 - [] is displayed on images shot with AEB.
 - With the EOS-1D series cameras, a []] is displayed on images with sound recorded.
 - You can change the software that starts up when you download images, from ZoomBrowser EX to Digital Photo Professional (p.1-10). However, if you have downloaded images following "Downloading Images Using Your Card Reader" (p.1-9), the software that can start up is limited to ZoomBrowser EX.



1-7

Remote Shooting

Troubleshooting

Downloading JPEG Images Using the PTP Function

Downloading for Cameras other than the EOS-1D Series Cameras

Downloading method for the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL and EOS DIGITAL REBEL/300D DIGITAL

When using Windows XP, you can use the PTP (Picture Transfer Protocol) function. When you set the camera's [Communication] and use the PTP function, you can download to your computer JPEG images saved in your camera's memory card without having to use EOS Utility.

This function is compatible with the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL and EOS DIGITAL REBEL/300D DIGITAL.

Check that the camera and the computer are not connected and then set the camera's power switch to <ON>.

Set the camera's [Communication].

Set the [Communication] for cameras in the same procedure as the "Setting a Camera with [Communication] Settings" (p.1-2), using the following for a reference.

[Communication] settings for different cameras

Camera model	Menu	Setting
• EOS 5D	[ft Communication]	[Print/PTP]
• EOS 30D	[ft Communication]	[Print/PC]
EOS 20D	[ft Communication]	[PTP]
EOS 10D	[Communication]	[PTP]
EOS DIGITAL REBEL XT/350D DIGITAL	[ft2 Communication]	[Print/PTP]
EOS DIGITAL REBEL/300D DIGITAL	[ft2 Communication]	[PTP]

Press the <MENU> button to switch the LCD monitor display off and then set the camera's power switch to <OFF>.

Connect the camera to the computer and set the camera's pow	ver
switch to <on> (p.1-3).</on>	

→ The window for selecting the software to use for downloading the images is displayed.

Select [Microsoft Scanner and Camera Wizard] and click the [OK] button.

→ The [Scanner and Camera Wizard] dialog box appears.

Download images as directed in the [Scanner and Camera Wizard] dialog box.

- With the PTP function, you cannot download RAW images.
- With the EOS 10D, you must change the firmware to version 2.0.0 or later. For details on changing, refer to the Canon's web site.

Downloading with EOS-1D Series Cameras


Downloading method for the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II

When using Windows XP, you can use the PTP (Picture Transfer Protocol) function by connecting the supplied USB interface cable to the camera's direct print terminal. By using the PTP function, you can download to your computer JPEG images saved in your camera's memory card without having to use EOS Utility.

This function is compatible with the EOS-1D Mark II N. EOS-1Ds Mark II and EOS-1D Mark II.

Plug the dedicated cable into the computer.

- Plug the cable into the USB port.
- Refer to the computer User's Manual for information on the terminal areas.



Plug the dedicated cable into your camera.

- Face the plug's < + → > mark towards the bottom of the camera and then connect the plug to the camera's direct print terminal.

Set the camera's power switch to <ON>.

→ The window for selecting the software to use for downloading the images is displayed.

Select [Microsoft Scanner and Camera Wizard] and click the [OK] button.

- The [Scanner and Camera Wizard] dialog box appears.
- Download images as directed in the [Scanner and Camera Wizard] dialog box.
- If you want to use the PTP function, connect with the USB interface cable supplied with the camera.
- With the PTP function, you cannot download RAW images.



Troubleshooting

Precautions for the PTP Function

- Uue to Windows XP specifications, you may experience the following restrictions with the PTP function. We recommend downloading shot images using EOS Utility (p.1-6).
 - RAW images cannot be downloaded.
 - (Even if RAW images are displayed, they cannot be downloaded.)
 - When a memory card in the camera contains both RAW images and JPEG images. you may not be able to download the JPEG images.
 - Shooting information for downloaded images may be altered or deleted.
 - Images cannot be downloaded if there is a large quantity of images in the camera (approximately 1,000 images).
 - It may take several minutes after connecting the camera and your computer until the PTP function is operational.
 - · Vertically shot images become horizontal when downloaded, or an image does not rotate even if you use the Rotate command.


In addition to the above restrictions, you may not be able to download images correctly depending on your OS version and computer environment.

Downloading Images Using Your Card Reader

You can also download images to the computer using a third-party card reader.

Load the card into the card reader.


- → The dialog box in step 2 appears.
- If the dialog box in step 2 does not appear, click the [Start] button ▶ select [All Programs] ([Programs] in Windows 2000) ▶ [Canon Utilities] ▶ [CameraWindow] ▶ [CameraWindowMC] ▶ [CameraWindow].



Select [View/Download Images using Canon CameraWindow] and then click the [OK] button.

→ CameraWindow MC (Image downloading) software for card readers) starts up.

images.



Cover/Table of

Contents

When downloading images to your computer using a third-party card reader without using Canon software such as EOS Utility or CameraWindow, refer to "Folder Structure and File Names" (p.5-4) and copy to your computer the folder with the shot images.

Transferring the Images in a Specified Folder

By inserting images in a transfer origin folder, the images can be transferred to the transfer destination folder and displayed in Digital Photo Professional or ZoomBrowser EX. In addition, when using the EOS dedicated Wireless Transmitter WFT-E1/E1A (optional), by specifying the folder where the shot images will be saved, you can check the shot images in Digital Photo Professional or ZoomBrowser EX in real time.

Click the [Monitor Folder] button.

→ The [Monitor Folder] dialog box appears.




The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected.

Set the transfer origin folder and the transfer destination folder.

Monitoring of the folder specified as the transfer origin is cancelled.








Setting the Cameras other than the EOS-1D Series Cameras

This chapter explains the functions that can be set in the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/350D DIGITAL, EOS DIGITAL REBEL/300D DIGITAL, EOS D60 and EOS D30.

For instructions on connecting your camera and computer, and for how to start EOS Utility, refer to Chapter 1 (p.1-3).

 Click on the item to display its page. Basic Settings 	2-2
Shot Settings	2-3
Picture Style	2-3
White Balance Adjustment	2-5



Cover/Table of



Basic Settings

You can perform settings on the camera, such as setting the camera owner's name and setting the date and time.

Click the [Camera settings/Remote shooting] button.

→ The camera settings window appears.




The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected.


Click [🙌].

- The basic settings window appears.
- Click again to close the basic settings window.

You can shoot photos remotely. For remote

shooting, refer to Chapter 4.








Shot Settings

You can apply various shot settings to the camera.



Cover/Table of

Troubleshooting

Index

2-3

The above window shows information displayable when the EOS 30D is connected. The displayed information varies depending on the camera model connected.

Detailed Settings

Click [Picture Style].

→ The [Picture Style] window appears.




Click [Settings].

→ The [Picture Style setting] dialog box appears.



Specify desired settings.



- You can register up to 3 user settings in your camera.
- When you select [Monochrome] in the [Picture Style] list box, the [Filter effect] and [Toning effect] list boxes appear.
- Refer to "Registering the Picture Style" in the camera's Instruction Manual for information about using the Picture Style registered in the camera.

Click the [Apply] button.

4

→ The [Confirm settings] dialog box appears.

Confirm the settings and click the [OK] button.

The settings are registered in the camera.

Click the [Close] button.

→ The [Picture Style setting] dialog box closes.

Select the specified user setting.

- Following the "Selecting a Picture Style" procedure (p.2-3), select the specified Picture Style.
- → The settings are applied to the camera, and the display returns to the shot settings window.
- A Picture Style file is a file that expands the Picture Style function. For detailed information on Picture Style file, refer to the Canon's web site.



Troubleshooting



White Balance Adjustment

You can compensate the white balance and apply it to the camera.

• This function is compatible with the EOS 5D, EOS 30D, EOS 20D and EOS DIGITAL REBEL XT/350D DIGITAL.


Click [WB SHIFT].

→ The white balance adjustment window appears.




Click the compensation position.

→ The settings are applied to the camera.



Click [👥].

- → The display returns to the shot settings window.
- To revert the corrected values to the original values, follow the procedure in step 2.





Setting the EOS-1D Series Cameras

This chapter explains the functions that can be set in the EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II, EOS-1Ds and EOS-1D.

For instructions on connecting your camera and computer, and for how to start EOS Utility, refer to Chapter 1 (p.1-4).

	n to display its page.	3-
Specifying the	Personal White Balance	3-
Specifying the	JPEG Quality	
White Balance	e Adjustment	3-
Specifying the	Parameters	3-
Specifying the	e Color Matrix	3-
Personal Funct	ion Settings	
Description of	Personal Functions	3-
Checking Per	sonal Function Settings	3-1
Saving and Lo	oading Personal Function Settings	3-1

Cover/Table of Contents			
Introduction			
Downloading Images from the Camera			
Setting the Cameras other than the EOS-1D Series Cameras			
Setting the EOS-1D Series Cameras			
Remote Shooting			
Troubleshooting			
Index			

Cover/Table of



Basic Settings

You can perform settings on the camera, such as setting the camera owner's name and setting the date and time.

Click the [Camera settings/Remote shooting] button.

→ The camera settings window appears.




The above window shows information displayable when EOS-1D Mark II N is connected. The displayed information varies depending on the camera model connected.


Click [97].

The basic settings window appears.

shooting, refer to Chapter 4.

Click again to close the basic settings window.








Shot Settings

You can apply various shot settings to the camera.



Cover/Table of

Index

3-3

 The above window shows information displayable when the EOS-1D Mark II N is connected. The displayed information varies depending on the camera model connected.

Detailed Settings

Click [Picture Style].

→ The [Picture Style] window appears.




Click [Settings].

→ The [Picture Style setting] dialog box appears.

	0 11	
Picture Style		
	Monochrome	
Portrait	User Defined1	
Landscape	User Defined2	
Neutral	User Defined3	
Faithful	Settings	
0) X	

Specify desired settings.



- You can register up to 3 user settings in your camera.
- When you select [Monochrome] in the [Picture Style] list box, the [Filter effect] and [Toning effect] list boxes appear.
- Refer to "Registering the Picture Style" in the camera's Instruction Manual for information about using the Picture Style registered in the camera.

Click the [Apply] button.

4

→ The [Confirm settings] dialog box appears.

Confirm the settings and click the [OK] button.


The settings are registered in the camera.

Click the [Close] button.

→ The [Picture Style setting] dialog box closes.

Select the specified user setting.

- Following the "Selecting a Picture Style" procedure (p.3-3), select the specified Picture Style.
- The settings are applied to the camera, and the display returns to the shot settings window.
- A Picture Style file is a file that expands the Picture Style function. For detailed information on Picture Style file, refer to the Canon's web site.





Specifying the Personal White Balance

Up to 3 white balance files saved with RAW Image Task can be registered in the camera as personal white balance.

- These functions are compatible with all EOS-1D series cameras.
- For how to save a white balance file with RAW Image Task, refer to "Processing RAW Images" in the ZoomBrowser EX Instruction Manual.
- When you register a personal white balance file to the camera, < P[- 1 > to < P[-3 > is displayed on the rear LCD display panel of the camera.
- For more information on setting the personal white balance on the camera, refer to "Selecting the White Balance" in the camera's Instruction Manual.


Click [Personal white balance].

 The [Personal white balance settings] dialog box appears.



>

Select the personal white balance to be registered.



Cover/Table of Click the [Open] button. Contents The [Open] dialog box appears. Personal white balance settings Personal white balance settings Introduction Personal white balance 1(PC-1): Not set Personal white balance 2(PC-2): Not set Personal white balance 3(PC-3): Not set Displays the setting status for the personal white balance registered > on the camera along with their titles Personal white balance setting name Open. **Downloading Images** Title: from the Camera Close Closes the dialog box. Setting the Cameras Deletes the selected personal white balance from the camera. other than the EOS-1D Registers the selected personal white balance settings on the camera. Series Cameras Enter a title for the personal white balance to be registered. Open the folder containing the saved white balance file, select the file, and then click the [Open] button. Setting the EOS-1D Series Cameras The white balance file is loaded. Enter a title in the [Title] input box. Click the [Apply to camera] button. Remote Shooting → The personal white balance file is registered on the camera. To register another setting, repeat steps 2 to 6. You can register up to 3 settings (PC-1, PC-2 and PC-3). Click the [Close] button. Troubleshooting

→ The [Personal white balance settings] dialog box closes, and the display returns to the shot settings window.




Specifying the JPEG Quality

->

-

You can specify the JPEG quality and register the settings on the camera.

This function is compatible with the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II.



White Balance Adjustment

You can compensate the white balance and apply it to the camera.



Cover/Table of

Contents

Specifying the Parameters

You can upload sharpness and contrast settings as well as a tone curve file saved with RAW Image Task and register up to 3 of these in the camera as processing parameters.

- This function is compatible with the EOS-1Ds Mark II, EOS-1D Mark II, EOS-1Ds and EOS-1D.
- For how to save a tone curve file with RAW Image Task, refer to "Processing RAW Images" in the ZoomBrowser EX Instruction Manual.
- For more information on setting the processing parameters on the camera, refer to "Setting the Processing Parameters" in the camera's Instruction Manual.

Click [Parameters].

→ The [Parameters settings] dialog box appears.



Select a tab to be set.



3	Specify desired settings.		Cover/Table of Contents
	Tone Curve:	[Standard]: The standard tone curve is set.	Introduction
	User Defined Add TCD2 User Defined Add TCD3	[User Defined TCD1] to [User Defined TCD3]: You can apply the tone curve file saved in RAW Image Task. With the EOS-1Ds and EOS-1D, [User Defined] is displayed and you can select one tone curve file.	Downloading Images from the Camera
	0 1 2 3 4 5 Sharpness : -2 -1 0 +1 +2 Contrast :	Click the [Add] button and in the dialog box that appears, select the tone curve file saved on your computer.	Setting the Cameras other than the EOS-1D Series Cameras
	Apply to Camera Close	Applies the settings to the camera. Closes the dialog box.	Setting the EOS-1D Series Cameras
4	 With the EOS-1Ds and EOS-1D, [Sharped the item to be set from the list box. Click the [Apply to Camera] button. → The [Confirm settings] dialog box appears. Confirm the settings and click the [O 	Remote Shooting	
>	→ The processing parameter is registered on the	-	Troubleshooting
6	Click the [Close] button.		
	→ The [Parameters settings] dialog box closes, settings window.	, and the display returns to the shot	Index



Personal Function Settings


Specifying the Color Matrix

You can set the color matrix. You can also set in the camera up to 2 color matrix ([6CM set1] and [7CM set2]) that have color space, color saturation and color tone set optionally.

- This function is compatible with the EOS-1Ds Mark II and EOS-1D Mark II.
- For more information on setting the color matrix on the camera, refer to "Selecting the Color Matrix" in the camera's Instruction Manual.
- 1 Click [Color matrix]. → The [Color matrix] window appears. Parameters Parameters Parameters Color matrix 1Standard WB SHIFT 0.0 3
- Click the color matrix to be set in the camera.
 - The settings are applied to the camera, and the display returns to the shot settings window.
 - For the color space, color saturation and color tone of [6CM set1] or [7CM set2], click the [Settings] button and set in the [Color matrix settings] dialog box that appears.

	(1)
Color matrix :	
1Standard	5L-saturat.
2Portrait	6CM set1
3H-saturat.	7CM set2
4Adobe RGB	
	Settings
0	5 X

The optional settings [Color space], [Saturation] and [Color tone] in the [Color matrix settings] dialog box can only be set when [6CM set1] or [7CM set2] is selected in the [Color matrix] list box.



- → The selected window appears.
- In the [Combination] tab sheet, you can check the specified Personal Function settings and the status of whether or not the settings are applied to the camera. You can also save and load the Personal Function settings (p.3-14, p.3-15).


3-8

Checkmark the box [] and specify desired settings (p.3-9 to p.3-14).

- .Fn-01) Disables the shooting modes
- Disable shutter-priority AE
- Disable aperture-priority AE
- 📃 Disable manual exposure
- Disable bulb exposure
- If you enter a numerical value, values outside the valid range of settings are ignored.
- Check the settings and save them on your computer if necessary (p.3-14, p.3-15).

Click the [OK] button.

- → The settings are applied to the camera, the [Personal functions] dialog box closes, and the display returns to the basic settings window.
- → When a Personal Function is applied to the camera, <# > appears on the LCD panel.



Description of Personal Functions

 The Image shown in this section provides brief descriptions of the Custom Function Settings for the respective camera functions. For more details, refer to "Custom Function Settings" in the camera's Instruction Manual supplied with the camera.

P.Fn-01 Disables the shooting modes

- Checkmark the shooting modes you do not want to use.
- Unwanted shooting modes can be skipped while you are selecting the shooting mode.
- This makes selecting the desired shooting mode faster.
- With the EOS-1Ds and EOS-1D, [Disable depth-of-field AE] is also displayed.
- At least one checkbox must be left unchecked.

P.Fn-02 Disables the metering modes

- Checkmark the metering modes you do not want to use.
- Unwanted metering modes can be skipped while you are selecting the metering mode.
- This makes selecting the desired metering mode faster.

At least one checkbox must be left unchecked.

P.Fn-03 Specifies the metering mode for manual exposure

- Select the metering mode to be specified.
- You can specify the metering mode to be used in the manual exposure mode.
- When you set the manual exposure mode, the metering mode selected here will be set automatically. In the manual exposure mode, this enables you to use a metering mode different from the one used in the AE modes.

Cover/Table of Contents

Introduction

Downloading Images from the Camera

Setting the Cameras other than the EOS-1D Series Cameras

Setting the EOS-1D Series Cameras

Remote Shooting

Troubleshooting



P.Fn-04 Sets the maximum and minimum shutter speeds to be used

- Select the maximum and minimum shutter speeds from the list box.
 For example, if you set 1/2000 sec. as the fastest shutter speed and 1/60 sec. as the slowest, the shutter speed range will be 1/2000 to 1/60 sec.
- This makes shutter speed selection faster and prevents a slow-speed sync. in aperturepriority AE mode with the flash.
- If you set the maximum and/or minimum shutter speed to one that is not a full-stop increment (such as 1/750 sec.), the controllable and settable shutter speed range might not be as exact as you set it (A slight deviation may occur.). This applies if you also set Custom Function C.Fn-6-1 and C.Fn-6-2 and set the maximum and/or minimum shutter speed to one that is not a full-stop increment (such as 1/3200 sec.).
 - To ensure that a proper flash sync speed is set in the Program AE mode, a shutter speed range of 1/200 sec. to 1/80 sec. cannot be set with the EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II and EOS-1Ds, and the range of 1/400 sec. to 1/80 sec. cannot be set with the EOS-1D.
 - If safety shift has been enabled (with C.Fn-16), it will override P.Fn-04's shutter speed range.

P.Fn-05 Sets the maximum and minimum apertures to be used

- Select the maximum and minimum apertures from the list box.
 For example, if you set 1.4 for the largest aperture (minimum f/number) and 8.0 for the smallest aperture (maximum f/number), the usable aperture range will be f/1.4 to f/8.0.
- You can better control the apertures used by setting the range of usable apertures.
- Specify a minimum aperture value that is smaller than the maximum aperture setting. If you select a minimum aperture value that is larger than the maximum aperture, a warning message appears and the setting reverts to the default value.
- If you set the maximum and/or minimum aperture to one that is not a full-stop increment (such as f/4.5), the controllable and settable aperture range might not be as exact as you set it (A slight deviation may occur.). This applies if you also set Custom Function C.Fn-6-1 or C.Fn-6-2 and set the maximum and/or minimum aperture to one that is not a full-stop increment (such as f/6.3).
- If the largest aperture of the attached lens is smaller than the largest aperture you set with P.Fn-05, the largest aperture will be set to the lens' largest aperture. And if the largest aperture of the attached lens is smaller than the smallest aperture you set with P.Fn-05, the aperture will be set and fixed to the lens' largest aperture.
- If safety shift has been enabled (with C.Fn-16), it will override P.Fn-05's aperture range.

P.Fn-06 Registers and switches the shooting mode and metering mode


- Only while you press the < >> button, you can switch to the preset shooting mode, exposure setting (such as the aperture for aperture-priority AE), metering mode, and exposure compensation amount.
- Select settings that are appropriate for each shooting mode.
- The modes and settings are preset with the camera.
- Convenient when you want to instantly select the preset modes and settings to suit a particular shooting situation such as backlit or front-lit conditions.

P.Fn-06 Registering the Modes and Settings with the Camera


Set the shooting mode and shooting mode settings (for example, aperture setting for aperture-priority AE mode). Then set the metering mode and exposure compensation amount.

Register the modes and settings.

 First press the < ⋈ > button, then press the < ⋈< > button.



- → < □ >appears in the LCD panel, indicating that the modes and settings have registered.
- The registered modes and settings can be modified any number of times.



- To register the modes and settings, first press the < 2 > button before the < 2 > button. If you press the < 2 > button first, the camera will only select the registered modes and settings instead.
 - Bulb cannot be preset.
 - You cannot select the registered modes and settings during continuous shooting.
 - If P.Fn-03 has been set to specify the metering mode for manual exposure, and P.Fn-06 is used to register the manual exposure mode and a metering mode different from the one specified with P.Fn-03, you can select the metering mode specified with P.Fn-03 by pressing the < > button.
 - If P.Fn-04 and/or P.Fn-05 has been set, set the shutter speed and aperture within the range specified with P.Fn-04 and/or P.Fn-05.
 - If the shooting and metering modes you want to set are excluded by the restrictions in P.Fn-01 and P.Fn-02, those Personal Functions must be disabled. For information on clearing and resetting Personal Functions, refer to "Clearing and Resetting Personal Functions" in the camera's Instruction Manual supplied with the camera.
 - Even if the shooting and metering modes selected by P.Fn-06 are excluded by the restrictions in P.Fn-01 and P.Fn-02, they are still valid for P.Fn-06.
- C.Fn
 If C.Fn-4-1 or C.Fn-4-3 has been set, AF and AE will also take effect when you press the < [...]> button.
 - When C.Fn-18 is set, P.Fn-06 is disabled.

	Contentis		
	ntroduction		
	wnloading Images n the Camera		
oth	tting the Cameras er than the EOS-1D ries Cameras		
	ting the EOS-1D ries Cameras		
R	emote Shooting		
Tro	oubleshooting		
	Index		

Cover/Table of

Contonto

P.Fn-07 Repeats bracketing during continuous shooting

- While you hold down the shutter button, bracketing repeats continuously in the currently selected drive mode.
- This function is useful when you want to continuously repeat the bracketing sequence.

P.Fn-08 Sets the number of shots to be bracketed

- Select the number of shots from the list box.
- The usual 3-shot bracketing is changed to 2-, 3-, 5-, or 7-shot bracketing.
- In bracketing shots, if you select 5-shot bracketing with 1-stop increment, the bracketing for the shots is -2, -1, 0, +1 and +2.
- This function is useful for adjusting the range of bracketing.
- Even when the setting is outside the bracketing level display range, the exposure is compensated as specified.
 - This function can be used in combination with C.Fn-09-2/3 and P.Fn-09.

P.Fn-09 Changes the bracketing sequence for C.Fn-09-2/3 to increased exposure, standard exposure, and decreased exposure


- The bracketing sequence when C.Fn-09-2/3 is selected (decreased exposure → standard exposure → increased exposure) changes to increased exposure → standard exposure → decreased exposure.
- This function is useful when you want to start the bracketing sequence with a increased exposure.

This function can be used in combination with P.Fn-08.

P.Fn-10 Retains the shift amount for program shift

- Normally, any program shift amount is canceled after you take the picture. This Personal Function retains the program shift amount.
- This function is useful when you want to shift the standard program line so that priority is given to the shutter speed or to the aperture.

By shifting the program, you can change the shutter speed or aperture and still retain the same exposure level. Under the same brightness, you can shift the program line toward the right to set a faster shutter speed and a larger aperture (lower f/number). Or you can shift the program line toward the left to set a slower shutter speed and a smaller aperture (higher f/number). P.Fn-10 retains the amount of program shift. Select the appropriate amount of shift for the level of priority you want to give to the shutter speed or aperture setting.



With EF50mm f/1.4 USM

- The program shift amount remains in effect until you set it back to the standard program manually or replace the battery or press the <CLEAR> button.
- The shift amount is retained even after you change the lens.

P.Fn-13 Executes AI Servo AF continuous shooting giving priority to the drive speed

- This function is compatible with the EOS-1D only.
- During continuous shooting, shutter release-priority takes effect instead of focus-priority.
- Effective when it is more important to capture an image even though it might be slightly out
 of focus.



Cover/Table of



3-11

P.Fn-14 Disables focus detection (search driving) by the lens drive

- Normally, when you press the shutter button halfway and focus cannot be achieved, the lens is driven to search the correct focus. This lens driving operation can be turned off.
- When focus has been achieved once and refocusing fails, the subsequent lens driving operation can result in grossly out of focus. This subsequent lens driving operation is turned off. P.Fn-14 is especially suited for super telephoto lenses.
- If autofocusing is attempted while the lens is way out of focus, the lens may stop operating. Focus manually until the subject outline becomes discernable, then autofocus.

P.Fn-15 Disables the AF-assist beam from being emitted

- This disables the external Speedlite's built-in AF-assist beam.
- At a joint photo session, etc., this prevents the AF-assist beam's pattern projected on the subject from being photographed by other photographers.

P.Fn-16 Enables automatic shooting when focus is achieved at the fixed point of focus while the shutter button is pressed fully

- This takes the picture automatically when the subject comes to the preset focusing distance.
 Focusing detection is performed using the selected AF point.
- Set the lens focus mode switch to <MF> and focus manually at the desired point of focus.
- Keep pressing the shutter button fully.
- Using an accessory such as Remote Controller RS-80N3 which can lock the shutter button relieves you from holding down the shutter button while you wait for the subject.
- Because the camera remains on standby while the shutter button is fully pressed, battery power is used up more quickly. For long periods of photography, use the DC Coupler Kit supplied with the camera.
- When this function is used in combination with a flash, the flash remains on standby at full charge. Consequently, the flash batteries are used up more quickly. (The Speedlite's SE mode is disabled.)
- When you use a flash with this function, set the drive mode to single shooting. If you select continuous shooting, the flash will be unable to charge in time for successive shots and will not fire at full charge.
- If you set the drive mode to continuous shooting, set the number of shots in P.Fn-20. If you do not use P.Fn-20, once the camera focuses on the subject, continuous shooting will continue until the capacity of the memory card is reached.
- P.Fn-16 cannot be used with manual focus lenses or with lenses that are too slow to be used with autofocusing.
- Do not use this function when C.Fn-4-1/3 is set as shots will be taken regardless of whether the image is in focus.

Using an accessory such as Remote Controller RS-80N3 which can lock the shutter button is recommended.

P.Fn-17 Disables automatic AF point selection

- When you select beyond the peripheral AF point, the selection stops there. It makes selecting a peripheral AF point faster.
- If C.Fn-11-2 has been set, you can switch to automatic AF point selection by pressing the < III > button during autofocusing. For more details, refer to "Selecting the AF Point" in the camera's Instruction Manual supplied with the camera.
 - If automatic AF point selection has been preset at [AF frame registration] setting, the preset setting remains valid. For more details, refer to "Registering and Switching the AF Point" in the camera's Instruction Manual supplied with the camera.

P.Fn-18 Enables automatic AF point selection when C.Fn-11-2 has been set

- Enables the standard horizonal AF point selection together with automatic AF point selection with C.Fn-11-2.
- Convenient when you want to use automatic AF point selection while C.Fn-11-2 has been set.
- If P.Fn-17 [Disables automatic AF point selection] has also been set, P.Fn-17 will override P.Fn-18 to disable automatic AF point selection.

P.Fn-19 Sets the continuous shooting speed

- In the list box, select the speed of continuous shots during continuous shooting.
- By reducing the maximum continuous shooting speed, AI Servo AF continuous shooting can be more stable.
- With the EOS-1Ds Mark II and EOS-1Ds, only [Continuous Shooting] is displayed.

In AI Servo AF, it may not be possible to complete the selected speed of continuous shots.

P.Fn-20 Limits the number of shots during continuous shooting

- This enables you to enter the maximum number of shots to be exposed during continuous shooting while the shutter button is pressed fully.
- Convenient when you do not want to shoot an unwanted scene that follows.

Cover/Table of Contents

Introduction

Downloading Images from the Camera

Setting the Cameras other than the EOS-1D Series Cameras

Setting the EOS-1D Series Cameras

Remote Shooting

Troubleshooting

Index

3-12

- P.Fn-21 Enables quiet operation when the shutter button is OFF after picture-taking
- When single shooting is selected, this function selects quiet camera operation when you release the shutter button from the fully pressed position to the half way position.
- This is useful when the camera operation noise would be disturbing after you take the picture.
- If you select continuous shooting, the camera operates normally.

C.Fn Setting mirror lockup with C.Fn-12 will further reduce the shooting noise.

P.Fn-23 Changes the timer's time length

- After you press and release a button, the respective function remains active for a specific number of seconds. You can change this number of seconds as necessary.
- The function's activation time can be set from 0 to 3600 sec. (1 hour).
- If the standard activation time is too short or too long, you can adjust it.

6 sec. timer	 AE lock time after you press the shutter button halfway or the < * > button.
16 sec. timer	FE lock time after you press the < FEL > button.
Post-shutter release timer (2 sec. timer)	 Exposure setting retaining time after the picture is taken. Setting this to a longer time can make it easier to shoot in the same exposure with AE lock. LCD panel illumination time after the picture is taken.

- Note that if you set a longer activation time, the battery become exhausted more quickly and the number of possible shots will be reduced.
- To turn off the function's activation time midway, press the < MODE > button, < AF > button or < ③ ₩ > button.

P.Fn-24 Illuminates the LCD panel during bulb exposures

- After the bulb exposure starts, press the <LCD panel illumination> button to illuminate the LCD panel until the bulb exposure ends.
- Convenient when you want to monitor the elapsed bulb exposure time.
- Note that if you take bulb shots for long periods, the battery becomes exhausted more quickly and the number of possible shots will be reduced.

P.Fn-25 Sets the default settings when the <CLEAR> button is ON

- You can use this function to select the default settings when you press the <CLEAR> button.
- Convenient when you want to instantly switch to frequently-used settings.

P.Fn-26 Shortened release time lag

- This function is compatible with the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II.
- Normally, the shutter-release time lag is controlled for stability. This Personal Function eliminates this control. As a result, the shutter-release time lag can be reduced by as much as about 20 percent when the aperture needs to be stopped down by no more than 3 stops.
- This is effective when a shorter shutter-release time lag is more important than a stable shutter-release time lag.
- Since the difference is in 10-millisecond increments, the time lag may not feel any shorter.

P.Fn-27 Enables the electronic dial's function to be used in the reverse direction

- The electronic dial's rotational function can be reversed for selecting the AF point and setting the shutter speed and aperture.
- By matching the dial's rotation direction to the particular operation, the operation can feel more intuitive.

When the Main Dial's rotational function is reversed, the horizontal AF point selection direction does not change.

P.Fn-28 Prevents exposure compensation with the Quick Control Dial

- The Quick Control Dial cannot be used to set exposure compensation.
- This prevents exposure compensation from being set accidentally while the AF point is being selected.



Cover/Table of

Contents



P.Fn-30 Enables Quick Control Dial switch to turn on/off Main Dial, too

- This function is compatible with the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II.
- Setting the Quick Control Dial switch to <OFF> disables the Main and Quick Control Dials.

P.Fn-30 Enlargement mode

- This function is compatible with the EOS-1Ds only.
- Select which part of an image is enlarged.
- If you take the shot on the camera with this function [ON], you can enlarge an image.
- For more imformation on using this function on the camera, refer to "P.Fn-30 Enlarging the image" in the EOS-1Ds Instruction Manual.
- If you wish to enlarge an image, set P.Fn-30 to [ON] during shooting and playback. The image shot on the camera without setting P.Fn-30 to [ON] cannot be enlarged.
 - The image shot on any camera other than the EOS-1Ds cannot be enlarged.

P.Fn-31 Add original decision data

- This function is compatible with the EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II and EOS-1Ds.
- The data that shows whether or not the image is the original one can be added to the image. When selecting the display format of Shooting information (INFO), the [] icon showing the captured image with Original image verification data is displayed.

For more details, refer to "Shooting Information Display" in the camera's Instruction Manual.

- To verify whether the image is the original, you will need the EOS dedicated accessory Data Verification Kit DVK-E2 (optional).
- The original decision data cannot be added to the JPEG or TIFF image converted from the RAW image.

Cover/Table of **Checking Personal Function Settings** Contents You can check the specified Personal Functions and the status of whether or not the settings are applied to the camera. Introduction Specify the Personal Functions (p.3-8 to p.3-14). Select the [Combination] tab. **Downloading Images** → The [Combination] tab sheet appears. from the Camera rsonal functions Exposure functions 1 Exposure functions 2 Evons an functions 3 AF functions Drive functions Combination Other functions 2 Other functions Check the settings. Setting the Cameras other than the EOS-1D You can check the Personal Function rsonal functions Series Cameras settings and check if these settings are Exposure functions 2 Exposure functions 3 Exposure functions 1 AF functions Drive functions applied on the camera. Combinatio Other functions 2 Other functions 3 Current settings :Not applied to camera Setting the EOS-1D P.En-01-1 Disables the shooting modes P.Ph-01-1: Disables the shorting modes P.Ph-025: Disables the motivity mode in menual encourse: Certer-P.Ph-025: SaceTes the metering mode in shorter specific bits built p.Ph-025: SaceTes and p.Ph-026 in the shorter specific bits built p.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters the shorter mode and metering in P.Ph-026: Registers and shorters and the shorter mode and metering in P.Ph-026: Registers and shorters and the shorter mode and metering in P.Ph-026: Registers and shorters and the shorter mode and metering in P.Ph-026: Registers and shorters and the shorter mode and metering in P.Ph-026: Registers and shorters and the shorter mode and t Series Cameras Remote Shooting Save As. Load settings lecet Apply to camera OK Cancel Troubleshooting You can load the Personal Function settings saved on your computer (p.3-15). You can save the specified Personal Function settings (p.3-15). Index



Saving and Loading Personal Function Settings


You can save the specified Personal Function settings on your computer as a Personal Function settings file and then load the saved Personal Function settings file and apply the settings to the camera.

Saving the Settings on Your Computer

- Click the [Save as] button.
- → The [Save As] dialog box appears.
- 2 Select the destination folder, enter the file name, and then click the [Save] button.
 - → The specified Personal Function settings are saved to the computer as a Personal Function settings file.
- The Personal Function settings file is not compatible with a camera other than the one the function was set.
- To update an existing Personal Function settings file, click the [Save] button.
- Personal Function settings file saved in your computer is compatible with both Windows and Macintosh.

Loading the Settings Saved on Your Computer

- Click the [Open] button.
 - → The [Open] dialog box appears.




Cover/Table of

Contents

3-15

- Open the folder containing the settings, select the file, and then click the [Open] button.
 - → The saved Personal Function settings file is loaded.
- Click the [OK] button.
- → The loaded settings are applied to the camera, the [Personal functions] dialog box closes, and the display returns to the basic settings window.
- → When a Personal Function is applied to the camera, <**#**> appears on the LCD panel.





This chapter explains how to take shots remotely by controlling from your computer.

For instructions on connecting your camera and computer, and for how to start EOS Utility, refer to Chapter 1 (p.1-1).

 To perform remote shooting and camera settings for a camera with [Communication] included as a menu function, you need to set the [Communication] according to the following table.

[Communication] settings for different cameras

Camera model	Menu	Setting
• EOS 5D	[ft Communication]	[PC connect.]
• EOS 30D	[ft Communication]	[Print/PC]
EOS 20D	[ft Communication]	[Normal]
EOS 10D	[Communication]	[Normal]
• EOS DIGITAL REBEL XT/350D DIGITAL	[ft2 Communication]	[PC connection]
EOS DIGITAL REBEL/300D DIGITAL	[ft2 Communication]	[Normal]

For instructions on settings, refer to "Setting a Camera with [Communication] Settings" (p.1-2).

Click on the item to display its page.

Remote Shooting 4-1
Single Shooting 4-1
Timer Shooting 4-2
Interval Timer Shooting 4-2
Specifying the Camera Settings 4-3
Specifying Preferences 4-3

Remote Shooting

Single Shooting

You can take a shot by remote controlling your camera from a computer.

Click the [Camera settings/Remote shooting] button.

 → The camera settings window appears.
 When switching to the main window, select the [Window] menu ▶ [Main Window].

t Cos Utility - Canon EOS XXX Downloads using camera Downloads using computer Downloads using computer Starts to download images Lets you select and download images Camera settings/Remote shooting Montor folder and impost images


Monitor Folde

C (B)

Preferences...

The above window shows information displayable when EOS 30D is connected. The displayed information varies depending on the camera model connected.


Quit



Cover/Table of Contents

Introduction






I-2 **() () ()**

Specifying the Camera Settings

You can check and change the settings in the camera from your computer remotely.




- The above window shows information displayable when the EOS 30D is connected. The displayed information varies depending on the camera model connected.
- Set the functions which you cannot set remotely (drive mode. AF mode etc.) directly in the camera.
- In the [Remote Shooting] tab sheet in the [Preferences], you can save shot images to both your computer and the memory card by setting [Save also to camera's memory card].

Click the icon to be set.

The icon displayed here shows exposure compensation as an example.



Use the buttons to change a value.



→ The changed settings are applied to the camera.

Before you specify the settings, be sure to check that the camera is ready for shooting. If the camera is not ready for shooting (the lens is not attached, etc.), you cannot make some of the settings.

Settable functions a	Cover/Table of				
	EOS-1D Mark II N EOS-1Ds Mark II EOS-1D Mark II EOS-1Ds	EOS 5D EOS 30D EOS 20D EOS DIGITAL REBEL XT/350D DIGITAL	EOS 10D EOS DIGITAL REBEL/ 300D DIGITAL	EOS-1D EOS D60 EOS D30	Contents
Shooting mode	0		0	0	Introduction
Shutter speed	0	0	0	0	-
Aperture	0	O	0	0	
White balance	O	O	0	0	
ISO speed	O	O	© *2	0	Downloading Images
Metering mode	0	0	0	0	from the Camera
Image recording quality	O	0	O	0	
Save destination of shot images	0	0	O	0	_
Exposure compensation	O	O	Ø	0	Setting the Cameras
Bracket shots	O *1	0	_	_	other than the EOS-1D Series Cameras
Drive mode	0	0	0	0	
AF mode	0	0	0	0	-
Battery status	0	0	0	0	Setting the EOS-1D
Warning display	0	0	0	0	Series Cameras
Shots to Go	0	0	0	0	

- O: Allows you to display camera settings and perform camera settings
- O: Allows you to display camera settings; camera settings not possible
- ^{*1}: Display with EOS-1Ds not possible
- *2 : Setting with EOS 10D not possible

Specifying Preferences

You can perform various EOS Utility settings.

- Select the [File] menu ▶ [Preferences]
 - The [Preferences] dialog box appears.

Specify desired settings and click the [OK] button.

The settings are applied to the EOS Utility.



Troubleshooting

This chapter provides troubleshooting and explains how to uninstall the software.

 Click on the item to display its page. 	
Troubleshooting	5-1
Uninstalling the Software	5-3
Uninstalling the Driver	5-3
Folder Structure and File Names	5-4
Index	5-4

Troubleshooting

If you could not complete the installation correctly, or communication between the camera and computer fails, or you connected the camera and computer before installing the software, consult the items described below.

• For instructions on installing, refer to the "Software Guide" supplied with the camera.

Installation failed.

- Are you using Windows XP under a setting other than [Computer administrator] privileges or using Windows 2000 under a setting other than [Administrator] privileges?
 - → You cannot install software if a user setting other than [Computer administrator] privileges or [Administrator] privileges is selected. Select the [Computer administrator] privileges user setting in Windows XP or the [Administrator] privileges user setting in Windows 2000. For detailed information on selecting the user setting, refer to your computer's instruction manual.

Is the cable firmly plugged into its socket?

→ To complete the installation, ensure that the plugs on the dedicated cable are securely plugged into the ports on the camera and computer when you connect the camera to your computer.

• Are the camera and computer set up correctly for communication?

- $\rightarrow\,$ Is the camera's power switch set to <ON>?
- → Even when the camera's power switch is set to <ON>, operation of the Auto power off function will automatically switch the camera off. To prevent this, set the Auto power off function to [Off]. For more details, refer to the camera's Instruction Manual supplied with the camera.

Does the [Add New Hardware Wizard] ([Found New Hardware Wizard] in Windows 2000) dialog box appear during installation?

 $\rightarrow\,$ Click the [Cancel] button, disconnect the dedicated cable, and then repeat the installation procedure from the beginning.

• Doesn't the installer panel appear?

→ Use the following procedure to display the installer panel.
 Click the [Start] button ▶ [My Computer]. (In Windows 2000, double-click [My Computer] on the desktop.) ▶ click on the CD-ROM drive containing the CD with the right button on the mouse ▶ select [Open] from the menu that appears ▶ double-click the icon on the right.



I have installed the software but the camera and computer cannot communicate.

Is the driver installed?

- → The driver is required for communication between the camera and computer. When you want to communicate between the camera and computer, be sure to install the driver shown below appropriate to your windows.
 - Windows XP: WIA Driver
 - Windows 2000: TWAIN Driver

• Have you installed the WIA Driver or TWAIN Driver?

→ Even if you have installed the WIA Driver or TWAIN Driver, installation is not completed unless the camera is connected to the computer. Insert the Solution Disk into the CD-ROM drive, install the WIA Driver or TWAIN Driver, and then connect the camera to your computer.

Does your computer comply with these requirements?

Cameras other than EOS-1D series cameras

- → Computer with Windows XP or Windows 2000 preinstalled and equipped with a USB port as a standard feature.
- * Operation is not guaranteed when a connection is used on computer systems other than those listed above.

EOS-1D series cameras

- → Computer with Windows XP or Windows 2000 preinstalled and equipped with an OHCI-compliant IEEE1394 port.
- * Operation is not guaranteed when a connection is used on computer systems other than those listed above.

Are the camera and computer connected correctly?

→ Connect the camera to your computer correctly using the dedicated cable (p.1-3, p.1-4).

Have you made the correct [Communication] settings for cameras that require [Communication] settings?

- → Set the camera's [Communication] to [PC connect.] or [PC connection] for the EOS 5D and EOS DIGITAL REBEL XT/350D DIGITAL, to [Print/PC] for the EOS 30D, and to [Normal] for the EOS 20D, EOS 10D and EOS DIGITAL REBEL/300D DIGITAL (p.1-2).
- * With the EOS 10D, you must also change the firmware to version 2.0.0 or later. For details on changing, refer to the Canon's web site.

Introduction
Downloading Images from the Camera
Setting the Cameras other than the EOS-1D Series Cameras
Setting the EOS-1D Series Cameras
Remote Shooting
Troubleshooting
Index

5-1

Cover/Table of Contents

Is there sufficient charge left in the camera battery?

→ Your computer does not supply power to the camera. Connect the AC Adapter Kit (optional) for the EOS 5D, EOS 30D, EOS 20D, EOS 10D, EOS DIGITAL REBEL XT/ 350D DIGITAL and EOS DIGITAL REBEL/300D DIGITAL, the DC Coupler supplied with the camera for the EOS D60 and EOS D30, and the DC Coupler Kit supplied with the camera for the EOS-1D series cameras. Alternatively, insert a fully charged battery and connect your computer and camera.

• Do you have more than one camera connected to your computer?

If you connect more than one camera to the same computer, the driver and camera may not operate normally.

- $\rightarrow\,$ Exit the software and disconnect all the dedicated cables. Then connect only one camera to the same computer again.
- Is the driver operating normally?

Connect the camera to your computer with the dedicated cable and set the camera's power switch to <ON> and open [Device Manager].

Click the plus symbol [+] to the left of [Imaging devices] and check that the connected camera is displayed.


→ If the connected camera is not displayed, the driver is not operating normally.

Briefly disconnect and then reconnect the dedicated cable, ensuring that the connection is secure. If the connected camera still does not appear, use the following procedure to re-install the driver.

- 1 Disconnect the dedicated cable and delete the driver (p.5-3).
- 2 Re-install the driver.
- → When the [X], [!] or [?] symbol is displayed beside the connected camera, part of the driver is missing or corrupted. Use the following procedure to re-install the driver.
 - 1 Delete the camera displayed in [Imaging devices].
 - 2 Disconnect the dedicated cable and delete the driver (p.5-3).
 - 3 Re-install the driver.

Is the driver installed correctly?

→ Connect the camera to your computer with the dedicated cable and set the camera's power switch to <ON> and open [Device Manager]. Click the plus symbol [+] to the left of [Other devices] or [Unknown devices] and check whether the connected camera or [Canon Digital Camera] is displayed.



- → If the connected camera or [Canon Digital Camera] is displayed in [Other devices] or [Unknown devices], the driver was not installed correctly. Use the following procedure to re-install the driver.
 - 1 Delete the camera or [Canon Digital Camera] displayed in [Other devices] or [Unknown devices].
 - 2 Disconnect the dedicated cable and delete the driver (p.5-3).
 - 3 Re-install the driver.

I connected the camera to the computer before installing the software

- Did you set the camera's power switch to <ON>?
 - \rightarrow If you did not set the camera's power switch to <ON>, proceed as follows:
 - 1 Disconnect the dedicated cable from the camera and computer.
 - 2 Install the Solution Disk software on your computer using the correct installation procedure and then connect the camera to your computer to complete the installation.
 - \rightarrow If you set the camera's power switch to <ON>, proceed as follows:
 - 1 If [Found New Hardware Wizard] or any other dialog boxes appear, click the [Cancel] buttons to cancel all the dialog boxes.
 - 2 Set the camera's power switch to <OFF>.
 - 3 Disconnect the dedicated cable from the camera and computer.
 - **4** Install the Solution Disk software on your computer using the correct installation procedure and then connect the camera to your computer to complete the installation.


To Display the Device Manager

Windows XP

→ Click the [Start] button ▶ select [Control Panel] ▶ [Performance and Maintenance]
 ▶ [See basic information about your computer]. Then select the [Hardware] tab and click the [Device Manager] button.

Windows 2000

→ Click the [Start] button ▶ select [Settings] ▶ [Control Panel]. Then double-click the [System] icon to open and select the [Hardware] tab and click the [Device Manager] button.



Cover/Table of

Contents

Uninstalling the Software

- Log in under [Computer administrator]/[Administrator] privileges when uninstalling the software.
- Before starting the software uninstallation, exit all programs you are using and disconnect the dedicated cable from your computer.
- To prevent computer malfunctions, always restart your computer after you have uninstalled the software. Re-installing the software without first restarting your computer is likely to result in computer malfunctions.
- Click the [Start] button ▶ select [All Programs] ([Programs] in Windows 2000) ▶ [Canon Utilities] ▶ [EOS Utility] ▶ [EOS Utility Uninstall].

Proceed with the uninstallation as directed by the on-screen messages.

→ Software is uninstalled.

Uninstalling the Driver

This section explains how to uninstall the EOS-1D Mark II N, EOS-1Ds Mark II, EOS 5D, EOS 30D, EOS 20D and EOS DIGITAL REBEL XT/350D DIGITAL driver. Refer to the software Instruction Manual supplied with the camera about deleting drivers in cameras other than those mentioned above.

- Log in under [Computer administrator]/[Administrator] privileges when uninstalling the driver.
- Before starting the driver uninstallation, exit all programs you are using and disconnect the dedicated cable from your computer.

Uninstall [EOS XXX WIA Driver] or [EOS XXX TWAIN Driver].

- Your camera model is displayed in EOS XXX.
- For Windows XP, click the [Start] button ▶ select [All Programs] ▶ [Canon Utilities] ▶ [EOS XXX WIA Driver] ▶ [WIA Driver Uninstall].
- For Windows 2000, click the [Start] button ▶ select [Programs] ▶ [Canon Utilities] ▶ [EOS XXX TWAIN Driver] ▶ [TWAIN Driver Uninstall].

stallShield Wizard

2

IlShield Wizard Complete

iver unstallation finished. Restart comp

emove any disks from their drives, and then click Finish t

Proceed with the uninstallation as directed by the on-screen messages.

→ The driver is uninstalled.

Restart the computer.

- When the dialog box on the right appears, select the [Yes, I want to restart my computer now.] and click [Finish] button.
- When the computer is restarted, uninstalling of the driver is completed.

those Introduction to the Downloading Images from the Camera ies] Setting the Cameras other than the EOS-1D Series Cameras Setting the EOS-1D Series Cameras Remote Shooting

Cover/Table of

Contents

Troubleshooting



Folder Structure and File Names

Images shot with the camera are saved in the memory card's [DCIM] folder, with the following folder structure and file names.

DCIM	xxxCANON	File name	than EOS-1D series cameras Image type/Camera used		
	or				
	xxxEOS5D	IMG_YYYY.JPG	JPEG image		
		IMG_YYYY.CR2	RAW	EOS 5D, EOS 30D, EOS 20D, EOS DIGITAL REBEL XT/350D DIGITAL	
		IMG_YYYY.CRW	image	EOS 10D, EOS DIGITAL REBEL/300D DIGITAL, EOS D60, EOS D30	
		CRW_YYYY.THM		Image for displaying the camera's index	
	 The "YYYY" in the file names represents a number between 			nes represents a number between 0001 and 9999	
	xxxEOS1D	File name	Image type/Camera used		
		****YYYY.JPG	JPEG image		
		****YYYY.CR2	RAW	EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II	
		****YYYY.TIF	image	EOS-1Ds, EOS-1D	
		****YYYY.WAV	Audio file		
	~	 appears in "****" The camera spears in the camera 	of the file cific char appears	acter string set at the time of factory shipment e name. acter string set at the time of factory shipment or in "****" of images shot with the EOS-1D Mark II N. nes represents a number between 0001 and 9999.	

- The "xxx" in the folder names represent a number between 100 to 999.
- The folder structure for the EOS-1D Mark II N, EOS-1Ds Mark II and EOS-1D Mark II CF card and SD card is the same.
- When you perform DPOF settings on the camera, a [MISC] folder is created. The files that manage the DPOF settings are saved in the [MISC] folder.

When Adobe RGB is specified, the file names of images shot with the EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II, EOS 5D, EOS 30D, EOS 20D and EOS DIGITAL REBEL XT/350D DIGITAL have an underbar " _ " as the first character.

Index

Α About the PTP Setting 1-2

В

Basic Settings 2-2, 3-2 Basic Settings Window 2-2, 3-2

С

Camera Settings Window ... 2-2, 3-2, 4-1, 4-3 **R** [Communication] Settings for Different Cameras 1-2, 1-8, 4-1 Compatible Models and Supported Images......0-1 Connecting the Camera to Your Computer 1-3, 1-4

D

Downloading All the Images in a Single
Operation 1-6
Downloading Images from Your Camera 1-6
Downloading Images to Your Computer by
Operating the Camera 1-6
Downloading Images Using Your Card
Reader 1-9
Downloading JPEG Images Using the PTP
Function 1-8
Downloading Selected Images 1-7
E

Exiting the Camera Settings Window

Exiting the EOS Utility 1-6, 1-7

F

Folder Structure and File Names...... 5-4

Initializing a Memory Card 2-2, 3-2

Ρ

Personal Function Settings...... 3-8

Checking Personal Function Settings... 3-14

Description of Personal Functions 3-9 Saving and Loading Personal Function

Settings...... 3-15

Detailed Settings	2-4, 3-4
Selecting a Picture Style	2-3, 3-3
Precautions for the PTP Function	1-9
Precautions When Connecting the Ca	amera
and Computer	1-5

W

Dicture Style

Remote Shooting
Interval Timer Shooting 4-2
Single Shooting 4-1
Timer Shooting 4-2
S
Settable Functions and Settings Displays by
Camera Model 4-3
Setting a Camera with [Communication]
Settings 1-2
Shot Settings 2-3, 3-3
Shot Settings Window 2-3, 3-3
Specifying Preferences 1-10, 4-3
Specifying the Color Matrix 3-8
Specifying the JPEG Quality 3-6
Specifying the Parameters 3-7
Specifying the Personal White Balance 3-5
Starting the Camera Settings Window
Starting up EOS Utility 1-3, 1-4
System Requirements 0-1
т
Transferring the Images in a Specified Folder
u –
Uninstalling the Driver
Uninstalling the Software

